# **Waveform Template**

This template is the oscilloscope's response to a TMPL? query:

```
/00
000000
                    LECROY_2_3: TEMPLATE
                    8 66 111
; Explanation of the formats of waveforms and their descriptors on the
; LeCroy Digital Oscilloscopes,
     Software Release 8.1.0, 98/09/29.
; A descriptor and/or a waveform consists of one or several logical data blocks
; whose formats are explained below.
; Usually, complete waveforms are read: at the minimum they consist of
        the basic descriptor block WAVEDESC
        a data array block.
; Some more complex waveforms, e.g. Extrema data or the results of a Fourier
; transform, may contain several data array blocks.
; When there are more blocks, they are in the following sequence:
        the basic descriptor block WAVEDESC
        the history text descriptor block USERTEXT (may or may not be present)
        the time array block (for RIS and sequence acquisitions only)
       data array block
       auxiliary or second data array block
; In the following explanation, every element of a block is described by a
; single line in the form
; <byte position> <variable name>: <variable type> ; <comment>
  where
   <byte position> = position in bytes (decimal offset) of the variable,
                      relative to the beginning of the block.
   <variable name> = name of the variable.
   <variable type> = string
                                    up to 16-character name
                                    terminated with a null byte
                        bvte
                                    08-bit signed data value
                        word
                                    16-bit signed data value
                                    32-bit signed data value
                        long
                       float
                                    32-bit IEEE floating point value
  with the format shown below
```

```
31 30 .. 23
                                                22 ... 0 bit position
;
                                     exponent fraction
                                  where
                                  s = sign of the fraction
                                  exponent = 8 bit exponent e
                                  fraction = 23 bit fraction f
                                  and the final value is
                                  (-1)**s * 2**(e-127) * 1.f
                    double
                                  64-bit IEEE floating point value
                                  with the format shown below
                                  63 62 .. 52 51 ... 0
                                                          bit position
                                     exponent fraction
                                  where
                                  s = sign of the fraction
                                  exponent = 11 bit exponent e
                                  fraction = 52 bit fraction f
                                  and the final value is
                                  (-1)**s * 2**(e-1023) * 1.f
                      enum
                                  enumerated value in the range 0 to N
                                  represented as a 16-bit data value.
                                  The list of values follows immediately.
                                  The integer is preceded by an _.
                 time_stamp
                                  double precision floating point number,
                                  for the number of seconds and some bytes
                                  for minutes, hours, days, months and year.
                                  double seconds
                                                    (0 to 59)
                                                    (0 to 59)
                                  byte minutes
                                                    (0 to 23)
                                  byte hours
                                  byte
                                         davs
                                                    (1 to 31)
                                  byte
                                         months
                                                    (1 to 12)
                                         year
                                  word
                                                    (0 to 16000)
                                  word
                                         unused
                                  There are 16 bytes in a time field.
                      data
                                  byte, word or float, depending on the
                                  read-out mode reflected by the WAVEDESC
                                  variable COMM_TYPE, modifiable via the
                                  remote command COMM_FORMAT.
                                  arbitrary length text string
                      text
;
                                  (maximum 160)
;
            unit_definition
                                  a unit definition consists of a 48 character
                                  ASCII string terminated with a null byte
                                  for the unit name.
WAVEDESC: BLOCK
; Explanation of the wave descriptor block WAVEDESC;
```

```
< 0>
              DESCRIPTOR NAME: string ; the first 8 chars are always WAVEDESC
< 16>
             TEMPLATE NAME: string
< 32>
             COMM_TYPE: enum
                               ; chosen by remote command COMM_FORMAT
                    byte
              __0
                    word
              _1
              endenum
< 34>
              COMM_ORDER: enum
              _0 HIFIRST
              _1
                    LOFIRST
              endenum
; The following variables of this basic wave descriptor block specify
; the block lengths of all blocks of which the entire waveform (as it is
; currently being read) is composed. If a block length is zero, this
; block is (currently) not present.
; Blocks and arrays that are present will be found in the same order
; as their descriptions below.
;BLOCKS :
< 36>
              WAVE_DESCRIPTOR: long ; length in bytes of block WAVEDESC
< 40>
             USER_TEXT: long ; length in bytes of block USERTEXT
< 44>
             RES_DESC1: long
; ARRAYS :
< 48>
            TRIGTIME ARRAY: long ; length in bytes of TRIGTIME array
< 52>
            RIS_TIME_ARRAY: long
                                     ; length in bytes of RIS_TIME array
< 56>
            RES_ARRAY1: long
                                     ; an expansion entry is reserved
< 60>
            WAVE_ARRAY_1: long
                                      ; length in bytes of 1st simple
                                      ; data array. In transmitted waveform,
                                      ; represent the number of transmitted
                                      ; bytes in accordance with the NP
                                      ; parameter of the WFSU remote command
                                      ; and the used format (see COMM_TYPE).
< 64>
            WAVE_ARRAY_2: long
                                     ; length in bytes of 2nd simple
                                      ; data array
< 68>
             RES_ARRAY2: long
< 72>
             RES_ARRAY3: long
                                  ; 2 expansion entries are reserved
```

```
; The following variables identify the instrument
< 76>
              INSTRUMENT_NAME: string
;
< 92>
              INSTRUMENT_NUMBER: long
< 96>
              TRACE_LABEL: string ; identifies the waveform.
<112>
              RESERVED1: word
<114>
              RESERVED2: word ; 2 expansion entries
; The following variables describe the waveform and the time at
; which the waveform was generated.
<116>
      WAVE_ARRAY_COUNT: long
                                     ; number of data points in the data
                                       ; array. If there are two data
                                       ; arrays (FFT or Extrema), this number
                                       ; applies to each array separately.
<120>
             PNTS_PER_SCREEN: long
                                      ; nominal number of data points
                                       ; on the screen
<124>
             FIRST_VALID_PNT: long ; count of number of points to skip
                                       ; before first good point
                                       ; FIRST_VALID_POINT = 0
                                       ; for normal waveforms.
<128>
             LAST_VALID_PNT: long
                                      ; index of last good data point
                                       ; in record before padding (blanking)
                                       ; was started.
                                       ; LAST_VALID_POINT = WAVE_ARRAY_COUNT-1
                                       ; except for aborted sequence
                                       ; and rollmode acquisitions
<132>
             FIRST_POINT: long
                                      ; for input and output, indicates
                                       ; the offset relative to the
                                       ; beginning of the trace buffer.
                                       ; Value is the same as the FP parameter
                                       ; of the WFSU remote command.
<136>
              SPARSING_FACTOR: long
                                      ; for input and output, indicates
                                       ; the sparsing into the transmitted
                                       ; data block.
                                       ; Value is the same as the SP parameter
                                       ; of the WFSU remote command.
<140>
              SEGMENT_INDEX: long
                                      ; for input and output, indicates the
                                       ; index of the transmitted segment.
                                       ; Value is the same as the SN parameter
```

```
; of the WFSU remote command.
<144>
               SUBARRAY_COUNT: long
                                      ; for Sequence, acquired segment count,
                                        ; between 0 and NOM_SUBARRAY_COUNT
<148>
              SWEEPS PER ACQ: long
                                       ; for Average or Extrema,
                                        ; number of sweeps accumulated
                                        ; else 1
<152>
              POINTS_PER_PAIR: word
                                     ; for Peak Dectect waveforms (which
always
                                        ; include data points in DATA_ARRAY_1
and
                                        ; min/max pairs in DATA_ARRAY_2).
                                        ; Value is the number of data points
for
                                        ; each min/max pair.
<154>
             PAIR OFFSET: word
                                       ; for Peak Dectect waveforms only
                                        ; Value is the number of data points by
                                       ; which the first min/max pair in
                                        ; DATA_ARRAY_2 is offset relative to
the
                                        ; first data value in DATA_ARRAY_1.
<156>
              VERTICAL GAIN: float
<160>
              VERTICAL_OFFSET: float ; to get floating values from raw data
                                       ; VERTICAL_GAIN * data -
VERTICAL_OFFSET
                                       ; maximum allowed value. It corresponds
<164>
             MAX_VALUE: float
                                       ; to the upper edge of the grid.
<168>
             MIN_VALUE: float
                                       ; minimum allowed value. It corresponds
                                       ; to the lower edge of the grid.
<172>
              NOMINAL_BITS: word
                                       ; a measure of the intrinsic precision
                                        ; of the observation: ADC data is 8 bit
                                            averaged data is 10-12 bit, etc.
<174>
              NOM_SUBARRAY_COUNT: word ; for Sequence, nominal segment count
                                        ; else 1
<176>
             HORIZ_INTERVAL: float
                                      ; sampling interval for time domain
                                        ; waveforms
<180>
             HORIZ_OFFSET: double
                                      ; trigger offset for the first sweep of
                                        ; the trigger, seconds between the
```

```
; trigger and the first data point
<188>
              PIXEL_OFFSET: double
                                        ; needed to know how to display the
                                        ; waveform
<196>
               VERTUNIT: unit_definition ; units of the vertical axis
<244>
              HORUNIT: unit_definition ; units of the horizontal axis
<292>
               HORIZ_UNCERTAINTY: float ; uncertainty from one acquisition to the
                                        ; next, of the horizontal offset in seconds
<296>
              TRIGGER_TIME: time_stamp ; time of the trigger
<312>
              ACQ DURATION: float
                                       ; duration of the acquisition (in sec)
                                        ; in multi-trigger waveforms.
                                        ; (e.g. sequence, RIS, or averaging)
<316>
              RECORD_TYPE: enum
              _0
                      single_sweep
               _1
                      interleaved
              _2
                      histogram
              _3
                      graph
                      filter_coefficient
                      complex
                      extrema
               _7
                       sequence_obsolete
              _8
                       centered_RIS
                      peak_detect
              endenum
<318>
              PROCESSING_DONE: enum
              _0
                      no_processing
               _1
                       fir_filter
                       interpolated
                       sparsed
                       autoscaled
                       no_result
               _6
                       rolling
               _7
                       cumulative
              endenum
<320>
              RESERVED5: word
                                    ; expansion entry
<322>
              RIS_SWEEPS: word
                                       ; for RIS, the number of sweeps
                                        ; else 1
; The following variables describe the basic acquisition
; conditions used when the waveform was acquired
```

<324>	TIMEB	ASE: enum
	_0	1_ps/div
	1	2_ps/div
	_2	5_ps/div
	_3	10_ps/div
	_	20_ps/div
	_4	
	_5	50_ps/div
	_6	100_ps/div
	_7	200_ps/div
	_8	500_ps/div
	_9	1_ns/div
	_10	2_ns/div
	_11	5_ns/div
	_12	10_ns/div
	_13	20_ns/div
	14	50_ns/div
	_	
	_15	100_ns/div
	_16	200_ns/div
	_17	500_ns/div
	_18	1_us/div
	_19	2_us/div
	_20	5_us/div
	_21	10_us/div
	_22	20_us/div
	_23	50_us/div
	_24	100_us/div
	_25	200_us/div
	_25 26	
	_	500_us/div
	_27	1_ms/div
	_28	2_ms/div
	_29	5_ms/div
	_30	10_ms/div
	_31	20_ms/div
	_32	50_ms/div
	_33	100_ms/div
	_34	200_ms/div
	_35	500_ms/div
	_36	1_s/div
	_37	2_s/div
	_38	5_s/div
	_39	10_s/div
	_	10_5/d1v
	_40	20_s/div
	_41	50_s/div
	_42	100_s/div
	_43	200_s/div
	_44	500_s/div
	_45	1_ks/div
	_46	2_ks/div
	_ _47	5_ks/div
	_100	EXTERNAL
	00	

```
endenum
<326>
             VERT_COUPLING: enum
             _0
                    DC_50_Ohms
             _1
                     ground
             _2
                     DC_1MOhm
             _3
                     ground
                     AC,_1MOhm
             _4
             endenum
<328>
             PROBE_ATT: float
<332>
             FIXED_VERT_GAIN: enum
             _0
                  1_uV/div
             _1
                  2_uV/div
                5_uV/div
             _3 10_uV/div
             _4 20_uV/div
             _5 50_uV/div
             _6 100_uV/div
             _7 200_uV/div
             _8 500_uV/div
             _9 1_mV/div
             _10 2_mV/div
             _11 5_mV/div
             _12 10_mV/div
             _13 20_mV/div
             _14 50_mV/div
             _15 100_mV/div
             _16 200_mV/div
             _17 500_mV/div
             _18 1_V/div
             _19 2_V/div
             _20 5_V/div
             _21 10_V/div
             _22 20_V/div
             _23 50_V/div
             _24 100_V/div
             _26 500_V/div
             _27 1_kV/div
             endenum
<334>
             BANDWIDTH_LIMIT: enum
             _0
                  off
             _1
                     on
             endenum
<336>
             VERTICAL_VERNIER: float
```

```
<340>
           ACQ_VERT_OFFSET: float
<344>
            WAVE_SOURCE: enum
                 CHANNEL_1
            _0
                 CHANNEL_2
            _1
            _2
                 CHANNEL_3
                  CHANNEL_4
            _9
                  UNKNOWN
            endenum
;
/00
             ENDBLOCK
USERTEXT: BLOCK
; Explanation of the descriptor block USERTEXT at most 160 bytes long.
< 0>
           TEXT: text
                               ; a list of ASCII characters
/00
             ENDBLOCK
TRIGTIME: ARRAY
; Explanation of the trigger time array TRIGTIME.
; This optional time array is only present with SEQNCE waveforms.
; The following data block is repeated for each segment which makes up
; the acquired sequence record.
                                ; for sequence acquisitions,
< 0>
            TRIGGER_TIME: double
                                ; time in seconds from first
                                ; trigger to this one
           TRIGGER_OFFSET: double ; the trigger offset is in seconds
                                ; from trigger to zeroth data point
/00
             ENDARRAY
RISTIME: ARRAY
; Explanation of the random-interleaved-sampling (RIS) time array RISTIME.
; This optional time array is only present with RIS waveforms.
; This data block is repeated for each sweep which makes up the RIS record
< 0>
           RIS_OFFSET: double
                            ; seconds from trigger to zeroth
```

```
; point of segment
/00
              ENDARRAY
DATA_ARRAY_1: ARRAY
;
; Explanation of the data array DATA_ARRAY_1.
; This main data array is always present. It is the only data array for
; most waveforms.
; The data item is repeated for each acquired or computed data point
; of the first data array of any waveform.
                                  ; the actual format of a data is
< 0>
           MEASUREMENT: data
                                  ; given in the WAVEDESC descriptor
                                  ; by the COMM_TYPE variable.
/00
              ENDARRAY
DATA_ARRAY_2: ARRAY
; Explanation of the data array DATA_ARRAY_2.
; This is an optional secondary data array for special types of waveforms:
                                   (real part in DATA_ARRAY_1)
      Complex FFT
                    imaginary part
      Extrema
                    floor trace
                                     (roof trace in DATA_ARRAY_1)
      Peak Detect
                   min/max pairs
                                     (data values in DATA_ARRAY_1)
; In the first 2 cases, there is exactly one data item in DATA_ARRAY_2 for
; each data item in DATA_ARRAY_1.
; In Peak Detect waveforms, there may be fewer data values in DATA ARRAY 2,
; as described by the variable POINTS_PER_PAIR.
< 0>
            MEASUREMENT: data
                                  ; the actual format of a data is
                                  ; given in the WAVEDESC descriptor
                                  ; by the COMM_TYPE variable.
/00
              ENDARRAY
SIMPLE: ARRAY
; Explanation of the data array SIMPLE.
; This data array is identical to DATA_ARRAY_1. SIMPLE is an accepted
; alias name for DATA_ARRAY_1.
< 0>
            MEASUREMENT: data
                                  ; the actual format of a data is
                                  ; given in the WAVEDESC descriptor
```

```
; by the COMM_TYPE variable.
/00
           ENDARRAY
DUAL: ARRAY
; Explanation of the DUAL array.
; This data array is identical to DATA ARRAY 1, followed by DATA ARRAY 2.
; DUAL is an accepted alias name for the combined arrays DATA_ARRAY_1 and
; DATA_ARRAY_2 (e.g. real and imaginary parts of an FFT).
          MEASUREMENT_1: data ; data in DATA_ARRAY_1.
< 0>
< 0>
         /00
           ENDARRAY
        ENDTEMPLATE
000000
```



BLANK PAGE